



View on some report in PLM360 in default.



After setup Show Values, isn't format of value OK.



Values are computed fields from the others fields with Data type – Float.

**Editing a Field**
Save Cancel

<b>Field name</b>	<input type="text" value="Stav v pokladně"/>	<small>The field name is the name you wish to be displayed on the workspace for this field.</small>
<b>Field ID</b>	<input type="text" value="STAV_V_POKLADNE"/>	<small>Automatically populated using Field Name. You can not edit the ID, and it must be unique to the workspace.</small>
<b>Field description</b>	<input style="width: 90%;" type="text" value="Výpočet = Příjmy - Výdaje"/>	<small>Enter the description you want to appear next to the field when users are creating or editing an item in the workspace.</small>
<b>Data Type</b>	<input type="text" value="Float"/>	<small>Select a format for the field, e.g., Date, Paragraph, Image etc.</small>
<b>Visible on preview</b>	<input type="checkbox"/>	<small>If checked, this field will be visible on the data-card preview</small>
<b>UOM</b>	<input checked="" type="radio"/> None <input type="radio"/> Imperial/Metric: <input type="text" value="grams"/> <input type="radio"/> Other: <input type="text"/>	<small>Type or select a uom. If a uom is selected then a conversion from metric to imperial or vice versa is displayed next to the field value. If a custom uom is typed in then that uom will be displayed next to the field.</small>
<b>Field length</b>	<input type="text" value="15"/>	<small>The maximum number of characters (or digits) this field can contain.</small>
<b>Field precision</b>	<input type="text" value="2"/>	<small>The maximum number of digits after the decimal point this field can contain.</small>
<b>Display width</b>	<input type="text" value="10"/>	<small>The maximum number of characters that will be displayed at one time.</small>
<b>Visibility</b>	<input type="text" value="Always"/>	<small>Determines when users will be able to view this field. Always means it will be displayed while creating, editing or viewing an item, Edit only means it will be visible during creating or editing an item.</small>
<b>Editable</b>	<input type="text" value="False"/>	<small>Determines if users will be able to edit this field. If false, the content is treated as HTML rather than text; please ensure the content is safe.</small>
<b>Default Value</b>	<input type="text"/>	<small>Define the default value for all occurrences of this field.</small>
<small>Define a formula to make this a computed field by using other Field IDs from this workspace. For Auto Numbers use your Field ID suffixed with *__AUTO_INC* to reference the underlying counter. Note: Other computed fields cannot be referenced in the formula.</small>		
<b>Computed Field Formula</b>	<input style="width: 90%;" type="text" value="PRIJEM_EC - VYDEJ_EC"/>	

Validation	Variables	Variable Values	Variable Description	Delete
<b>Decimal Number With Precision</b> <small>The value entered must be a valid positive or negative decimal number with a specified precision</small>				N/A
<a href="#">Add Validation...</a>				

Save Cancel

Pavel Zak, technical consultant  
[pavel.zak@cadstudio.cz](mailto:pavel.zak@cadstudio.cz)

CAD Studio a.s.  
 Autodesk Platinum Partner – CAD/GIS solutions  
 Libalova 1, Praha 4  
[www.cadstudio.cz](http://www.cadstudio.cz) [www.cadforum.cz](http://www.cadforum.cz) [blog.cadstudio.cz](http://blog.cadstudio.cz)

