Revit 2016 API

## PrintParameters Members

PrintParameters Class Methods Properties See Also Send Feedback

The PrintParameters type exposes the following members.

## **■ Methods**

	Name	Description
<b>≟</b>	<u>Dispose</u>	Causes the object to release immediately any resources it may be utilizing. (Inherited from <u>APIObject</u> .)
<b>≟</b>	<u>Equals</u>	Determines whether the specified <u>Object</u> is equal to the current <u>Object</u> .  (Inherited from <u>Object</u> .)
<b>≡</b>	<u>GetHashCode</u>	Serves as a hash function for a particular type. (Inherited from <u>Object</u> .)
<b>≡</b>	<u>GetType</u>	Gets the <u>Type</u> of the current instance. (Inherited from <u>Object</u> .)
<b>≡</b>	ToString	Returns a string that represents the current object. (Inherited from Object.)

## **■ Properties**

Name	Description
<u>ColorDepth</u>	The color depth type.
<u>HiddenLineViews</u>	The hidden line views type.
<u>HideCropBoundaries</u>	Indicates whether to hide crop boundaries when printing.
<u>HideReforWorkPlanes</u>	Indicates whether to hide reference/work planes when printing.
<u>HideScopeBoxes</u>	Indicates whether to hide scope boxes when printing.
<u>HideUnreferencedViewTags</u>	Indicates whether to hide unreferenced view tags when printing.
<u>IsReadOnly</u>	Identifies if the object is read-only or modifiable. (Inherited from <u>APIObject</u> .)
<u>MarginType</u>	The print margin type.
<u>MaskCoincidentLines</u>	Indicates whether to mask coincident lines when printing.
<u>PageOrientation</u>	The Page Orientation of the Print Setting.
<u>PaperPlacement</u>	The paper placement type.
<u>PaperSize</u>	The page size.
<u>PaperSource</u>	The page source.
<u>RasterQuality</u>	The raster quality type.
ReplaceHalftoneWithThinLines	Indicates whether to replace halftone with thin lines when printing.
<u>UserDefinedMarginX</u>	The User defined X value of offset from left bottom corner.
<u>UserDefinedMarginY</u>	The User defined Y value of offset from left bottom corner
<u>ViewLinksinBlue</u>	Indicates whether to view links in blue when printing.
<b>l</b>	İ

PrintParameters Members

Zoom	The zoom value to a percentage of the original size.
<u>ZoomType</u>	The zoom type.

## **■ See Also**

PrintParameters <u>Class</u> <u>Autodesk.Revit.DB Namespace</u>

Send comments on this topic to Autodesk